

```
#-----  
#   !!!      Note: By default this file has no effect.      !!!  
#  
#       To change any of the defaults, you must remove  
#       the '#' character on the line below the box.  
#       All the parameter values must be specified in UTF-8.  
#-----
```

```
#-----  
# Directory where error documentation is installed.  
# Default for (WIN32) is english\ndsimon\errors  
# Default for (NLM)   is sys:\login\nls\english\ndsimon\errors  
# Default for (UNIX)  is /usr/lib/ndsimon/errors  
#-----  
#DirError: sys:\login\nls\english\ndsimon\errors
```

```
#-----  
# Directory where help documentation is installed.  
# Default for (WIN32) is english\ndsimon\help  
# Default for (NLM)   is sys:\login\nls\english\ndsimon\help  
# Default for (UNIX)  is /usr/lib/ndsimon/help  
#-----  
#DirHelp: sys:\login\nls\english\ndsimon\help
```

```
#-----  
# Directory where images (icons, gifs, etc.) are installed.  
# Default for (WIN32) is images  
# Default for (NLM)   is sys:\login\  
# Default for (UNIX)  is /usr/lib/ndsimon/images  
#-----  
#DirImage: sys:\login\  
#-----
```

```
#-----  
# Directory where trace files are kept.  
# Default for (WIN32) is .\dstrace  
# Default for (NLM)   is sys:\system\dstrace  
# Default for (UNIX)  is /var/nds/dstrace  
#-----  
#DirTrace: sys:\system\dstrace
```

```
#-----  
# Novell-supported URL where error code documentation can be located.  
#-----  
#ErrorDocsURL: http://www.novell.com/documentation/lg/nwec/docui/index.html
```

```
#-----  
# Novell-supported URL where the user can search for information.  
#-----  
#SupportSearchURL: http://www.novell.com/search/support/kb\_index.html
```

```
#-----  
-----
```

```

# Novell-supported URL where the user can search for information on specified
errors. |
# The following options are appended together to form a query for errors like
this. |
#     SupportSearchErrorTidsURL Error Num SupportSearchErrorTidsURLQuery
|
#-----'
#SupportSearchErrorTidsURL:
http://search.novell.com/NSearch/SearchServlet?template=ResultListTerseTemplate.
html&numhits=20&theme=support&collection=Support&query=
#SupportSearchErrorTidsURLQuery: +(/Product_Class=Novell%20Directory%20Services)

#-----'
# Maximum number of concurrent trace files. |
#-----'
#MaxTraceFiles: 11

#-----'
# The Maximum Trace File Size is specified in bytes. |
#-----'
#MaxTraceFileSize: 2097152

#-----'
# To start trace automatically when NDSiMon is loaded, simply copy the options
# you want out of the query portion of the URL on the address line of your
# browser after visiting the trace options page and starting trace manually.
# Below is an example.
#-----'
#Trace Options:?iMonFormAction=Trace
On&Option=4&Option=5&Option=7&Option=10&Option=13&Option=15&Option=19&Option=21&
Option=23&Option=32&Option=34&Option=35&Option=36&Option=40&Option=43&Prefix=0&P
refix=1&Prefix=2

#-----'
# This switch is used to control access to the server.
# 0 -> Allows access based on rights. This implies that without
#     authenticating, this server can be used to view anything [public]
#     has rights to.
# 1 -> (default) Must be authenticated as a valid user.
# 2 -> Must be authenticated as a supervisor of this box.
# 4 -> Must be authenticated as a console operator of this box.
# 8 -> Allows access if DS is closed.
# Setting LockMask: 14 means they must be a supervisor or console operator,
# or allow access if DS is closed.
#-----'
LockMask: 1

#-----'
# Number of minutes of inactivity allowed before a connection is logged out.
# The default is 30 minutes.
# Note : This option controls the cached connection from NDSiMon to NDS,
# and allows iMon to reduce its resource requirements for users who have
# been idle for a long period of time. If a user rerequests information from

```

```
# the server after a prolonged idle period, it is possible that the browser
# will have retained cached credential information which will be used to
# reestablish the connection between iMon and NDS. To prevent the browser
# from retaining cached information, the user must close all instances of the
# browser. This option only applies to non-NetWare platforms.
```

```
#-----
#Login Connection Timeout: 30
```

```
#-----
# Maximum numbers of object to be displayed when listing a
# container, or displaying the search result.
```

```
#-----
#Max Object List: 3000
#Max Object List With Attrs: 1000
#Max Object List With Values: 50
```

```
#-----
# Enable/Disable display of Reference attribute.
```

```
# Enable = 1
# Disable = 0
```

```
#-----
#Browse Reference By Default: 0
```

```
#-----
# This switch is used to control whether or not a configuration page will
# restore an NDS Name (e.g. DN) to a text edit box from a previously saved
# configuration page.
```

```
# 0 -> (default) Restores the saved name to the configuration page. This
# implies that [public] might be able to see a name that would not
# otherwise be accessible if someone with supervisor rights had
# previously saved the configuration page with that name in it.
# 1 -> Must be authenticated as a supervisor of this box.
```

```
#-----
#CfgRestoreName: 0
```